



ACS/PDS UNISCOPE ACCESS

<u>DATA DESCRIPTION</u>	<u>SCREEN ACCESS</u>
VENDOR/GOV'T P/N - UNIVAC P/N Cross-Reference, FSCM	▷S24ΔVendor/Gov't P/N]
NATIONAL STOCK NUMBER (NSN) - UNIVAC P/N Cross-Reference	▷S25ΔNSN]
GENERIC/SPECIFICATION - UNIVAC P/N Cross-Reference	▷S30ΔGeneric/Spec.]
REFERENCE DESIGNATIONS Item Number, P/N, & Ref. Des.	▷S09ΔDocument Number]
PROVISIONING DATA Item Name, Vendor P/N, NSN, FSCM.	▷S12ΔPart Number]
BASE LINE INDEX DATA FSCM & Description, Doc. Title, Rev., PDS Number.	▷S15ΔDocument Number]
FSCM CROSS-REFERENCE Company/Individual Address	▷S68Δ0FSCM]
ITEM NUMBER ENGINEERING NOTES	▷S42ΔDocument Number, V]
DOCUMENT (General) ENGINEERING NOTES	▷S42ΔDocument Number, 1]
PARTS LIST HISTORY Item & Change Find Number, Old P/N, Qty.	▷S06ΔDocument Number]
HAND WIRE TAB DATA Origin/Destination Terminals, Use Items, Wire Data, ESN, Net (Including Remarks, Notes)	▷S10ΔDocument Number] ▷S101ΔDocument Number]
PDS NO. - P/N CROSS-REFERENCE P/N, Description (Including KLS & Class Control)	▷S11ΔPDS Number] ▷S113ΔPDS Number]
DOCUMENT NUMBER ASSIGNMENT	▷S22], S221]
PROJECT CODE - CONTRACT NUMBER Cross-Reference	▷S26ΔPC]
ACS MASTER SCREEN	▷P98ΔControl Number]
ACS FOR SPECIFIC DOCUMENT	▷P98ΔControl No.ΔDoc. No.]
ENGINEERING CHANGE PROPOSAL DATA	▷P42ΔControl Number]
FIELD CHANGE ORDER DATA	▷P44ΔControl Number]
RFC/EIR/STR DATA (By EIR Dash Number)	▷P45ΔControl Number] ▷P981ΔControl No.ΔDash No.]

For a self-aid help directory for the ACS system, enter: ▷ACS]

For a self-aid help directory for the PDS system, enter: ▷PDS]

For additional ACS/PDS user assistance, contact C. H. Kivinen,
Design Data Development, Plant 8, St. Paul, MN, X3992.



ACS/PDS UNISCOPE ACCESS

PRIMARY ENGINEERING UNISCOPE DISPLAY CODES

DATA DESCRIPTION

SCREEN ACCESS

GENERAL DOCUMENT DATA	▷S01△Document Number]
Description, Dash Number Range, Document Revision Level (REV), Project & Contract Number Codes (PC,CN), Data Control Group Code (EG), Fed. Mfr. Code (FSCM), ESD Code, Document Status & Type Codes, Vault Location of Master (VL).	
VARIABLE (Part Number) DATA	▷S02△Part Number]
Full Description (Nomenclature), Commodity Code, NSN, Hazard Code, Generic, MIL Spec, Gov't Part Number.	
NEXT HIGHER P/N or DOC USED-ON	▷S03△Part Number] or ▷S03△Document Number]
Item Number, Qty, Effective Point (PDS Number, S/N).	
PDS NUMBER USED-ON	▷S04△Part Number]
End Item PDS No., Part No. or ▷S04△Document Number]	
PL or DOCUMENT LIST	▷S05△Document Number]
Item Number, Document or P/N, Rev, Qty, Description. (Including Notes, Ref. Des.)	
	▷S054△Document Number]
SPECIFIC DEFINITION	▷S71]
(Elements same as above)	
DOCUMENT CHANGE HISTORY	▷S07△Document Number]
MCN/EIR Number, Category, Class, Rev, Effectivity (PDS Number, S/N). (Including Change Notes)	
	▷S071△Document Number]
EIR MASTER LOCATION	▷S32△Document Number]
EIR Number, Category, Class, Rev, Release Date, Location Code, Date (By Control Number)	
	▷S31△Control Number]
ACTIVE CHANGE STATUS DATA	▷P50△Document Number]
PDS S01 Document Data RFC/EIR Status, Revision (Including Dev/Wav/NSPAR Data)	
	▷P502△Document Number]
DEVIATIONS/WAIVERS/NSPARs	▷P48△Control Number]
Status Code, Customer FSCM, Effectivity (PDS Number, S/N).	

▷ = SOE (Start of Entry)

△ = Space

] = Cursor Position, Transmit

Part Number (P/N) = Document Number + Dash/Version Number