

**ACS/PDS UNISCOPE ACCESS****PRIMARY  
ENGINEERING UNISCOPE DISPLAY CODES**

<u>DATA DESCRIPTION</u>	<u>SCREEN ACCESS</u>
<b>GENERAL DOCUMENT DATA</b> . . . . . Description, Dash Number Range, Document Revision Level (REV), Project & Contract Number Codes (PC,CN), Data Control Group Code (EG), Fed. Mfr. Code (FSCM), Document Status & Type Codes, Vault Location of Master (VL).	▶S01△Docurftent Number <sup>⌈</sup>
<b>VARIABLE (Part Number) DATA</b> . . . . . Full Description (Nomenclature), Commodity Code, NSN, MIL Spec, Gov't Part Number.	▶S02△Part Number <sup>⌈</sup>
<b>NEXT HIGHER P/N or DOC USED-ON</b> . . . . . Item Number, Qty, or Effective Point (PDS Number, S/N).	▶S03△Part Number <sup>⌈</sup> or ▶S03△Document Number <sup>⌈</sup>
<b>PDS NUMBER USED-ON</b> . . . . . End Item PDS No., Part No. or	▶S04△Part Number <sup>⌈</sup> ▶S04△Document Number <sup>⌈</sup>
<b>PL or DOCUMENT LIST</b> . . . . . Item Number, Document or P/N, Rev, Qty, Description.	▶S05△Document Number <sup>⌈</sup>
<b>DOCUMENT CHANGE HISTORY</b> . . . . . MCN/EIR Number, Category, Class, Effectivity (PDS Number, S/N).	▶S07△Document Number <sup>⌈</sup>
<b>ACTIVE CHANGE STATUS DATA</b> . . . . . PDS S01 Document Data RFC/EIR Status, Revision (Including Dev/Wav/NSPAR Data) . . . . .	▶P50△Document Number <sup>⌈</sup> ▶P502△Document Number <sup>⌈</sup>
<b>DEVIATIONS/WAIVERS/NSPARs</b> . . . . . Status Code, Customer FSCM, Effectivity (PDS Number, S/N).	▶P48△Control Number <sup>⌈</sup>

▶ = SOE (Start of Entry)

△ = Space

⌈ = Cursor Position, Transmit

Part Number (P/N) = Document Number + Dash/Version Number

# ACS/PDS UNISCOPE ACCESS

<u>DATA DESCRIPTION</u>	<u>SCREEN ACCESS</u>
VENDOR/GOV'T P/N – UNIVAC P/N ... Cross-Reference, FSCM	▶S24ΔVendor/Gov't P/N <sup>∩</sup>
NATIONAL STOCK NUMBER (NSN) – UNIVAC P/N ..... Cross-Reference	▶S25ΔNSN <sup>∩</sup>
REFERENCE DESIGNATIONS ..... Item Number, P/N, & Ref. Des.	▶S09ΔDocument Number <sup>∩</sup>
PROVISIONING DATA ..... Item Name, Vendor P/N, NSN, FSCM.	▶S12ΔPart Number <sup>∩</sup>
BASE LINE INDEX DATA. .... FSCM & Description, Doc. Title, Rev., PDS Number.	▶S15ΔDocument Number <sup>∩</sup>
ITEM NUMBER ENGINEERING NOTES . DOCUMENT (General) ENGINEERING NOTES .....	▶S42ΔDocument Number, V <sup>∩</sup> ▶S42ΔDocument Number, 1 <sup>∩</sup>
PARTS LIST HISTORY ..... Item & Change Find Number, Old P/N, Qty.	▶S06ΔDocument Number <sup>∩</sup>
HAND WIRE TAB DATA. .... Origin/Destination Terminals, Use Items, Wire Data, ESN, Net (Including Remarks, Notes) .....	▶S10ΔDocument Number <sup>∩</sup> ▶S101ΔDocument Number <sup>∩</sup>
PDS NO. – P/N CROSS-REFERENCE .... P/N, Description (Including KLS & Class Control) .....	▶S11ΔPDS Number <sup>∩</sup> ▶S113ΔPDS Number <sup>∩</sup>
DOCUMENT NUMBER ASSIGNMENT ...	▶S22 <sup>∩</sup> , S221 <sup>∩</sup>
PROJECT CODE – CONTRACT NUMBER CROSS-REFERENCE .....	▶S26ΔPC <sup>∩</sup>
ACS MASTER SCREEN .....	▶P98ΔControl Number <sup>∩</sup>
ACS FOR SPECIFIC DOCUMENT .....	▶P98ΔControl No.ΔDoc. No. <sup>∩</sup>
ENGINEERING CHANGE	
PROPOSAL DATA .....	▶P42ΔControl Number <sup>∩</sup>
FIELD CHANGE ORDER DATA .....	▶P44ΔControl Number <sup>∩</sup>
RFC/EIR/STR DATA .....	▶P45ΔControl Number <sup>∩</sup>
(By EIR Dash Number) .....	▶P981ΔControl No.ΔDash No. <sup>∩</sup>

For a self-aid help directory for the ACS system, enter: ▶ACS<sup>∩</sup>  
 For a self-aid help directory for the PDS System, enter: ▶PDS<sup>∩</sup>  
 For additional ACS/PDS user assistance, contact C. H. Kivinen,  
 Technical Documentation Control, Plant 8, St. Paul, MN, X3992.

T25 COST